



# 165

# CICS

*August 1999*

---

## **In this issue**

- 3 Auto-install for printers
  - 10 Analysing DSNC abends
  - 15 Accessing CEDA from ISPF
  - 26 CEMT logger – an alternative design
  - 37 Dealing with program abends – part 2
  - 48 CICS news
- 

© Xephon plc 1999

update

# ***CICS Update***

---

## **Published by**

Xephon  
27-35 London Road  
Newbury  
Berkshire RG14 1JL  
England  
Telephone: 01635 38030  
From USA: 01144 1635 38030  
E-mail: info@xephon.com

## **North American office**

Xephon/QNA  
1301 West Highway 407, Suite 201-405  
Lewisville, TX 75077-2150  
USA  
Telephone: 940 455 7050

## **Contributions**

Articles published in *CICS Update* are paid for at the rate of £170 (\$250) per 1000 words and £90 (\$140) per 100 lines of code for original material. To find out more about contributing an article, without any obligation, please contact us at any of the addresses above and we will send you a copy of our *Notes for Contributors*.

## ***CICS Update* on-line**

Code from *CICS Update* can be downloaded from our Web site at <http://www.xephon.com/cicsupdate.html>; you will need the user-id shown on your address label.

## **Editor**

Robert Burgess

## **Disclaimer**

Readers are cautioned that, although the information in this journal is presented in good faith, neither Xephon nor the organizations or individuals that supplied information in this journal give any warranty or make any representations as to the accuracy of the material it contains. Neither Xephon nor the contributing organizations or individuals accept any liability of any kind howsoever arising out of the use of such material. Readers should satisfy themselves as to the correctness and relevance to their circumstances of all advice, information, code, JCL, and other contents of this journal before making any use of it.

## **Subscriptions and back-issues**

A year's subscription to *CICS Update*, comprising twelve monthly issues, costs £175.00 in the UK; \$270.00 in the USA and Canada; £181.00 in Europe; £187.00 in Australasia and Japan; and £185.50 elsewhere. In all cases the price includes postage. Individual issues, starting with the January 1994 issue, are available separately to subscribers for £16.00 (\$23.50) each including postage.

---

© Xephon plc 1999. All rights reserved. None of the text in this publication may be reproduced, stored in a retrieval system, or transmitted in any form or by any means, without the prior permission of the copyright owner. Subscribers are free to copy any code reproduced in this publication for use in their own installations, but may not sell such code or incorporate it in any commercial product. No part of this publication may be used for any form of advertising, sales promotion, or publicity without the written permission of the publisher. Copying permits are available from Xephon in the form of pressure-sensitive labels, for application to individual copies. A pack of 240 labels costs \$36 (£24), giving a cost per copy of 15 cents (10 pence). To order, contact Xephon at any of the addresses above.

*Printed in England.*

## Auto-install for printers

Are you frustrated with unnecessary printer definitions because you don't know which definition to delete? So were we – until we came up with this idea to define printers automatically as our clerks log on.

### CICS REQUIREMENT

This solution will only work from CICS 4.1 upwards because of the CREATE command and the terminal auto-install program in the AOR. We run in an MVS 5.2 environment.

### OUR PRINTER ENVIRONMENT

We have printers defined in our TOR for print screens (CSPK). We also have printer definitions in some of our AORs for CICS transactions that run on printers.

Our standard for printer names is as follows. The terminal ID is cut from the first four characters of the netname. The first three characters of the terminal ID is called a string. Each unique string has one printer defined to it. This printer, known as the default printer, always has '2' in the fourth character. For example, terminals AF01, AF03, or AF08 all belong to printer AF02.

We use a terminal auto-install program to define all our terminals in the TOR. Also, in the AOR, we run the auto-install program to define a surrogate TCT entry when transaction routing executes. We have approximately 4,000 printers defined in our TCT. We are notified by the network team of each printer definition, but we are not always notified when a string of terminals are taken out of use. For special cases of print screen (CSPK) the printout needs to be printed elsewhere, rather than on the default printer. For this situation, we have a file (SPRN) that contains a list of override printers for each terminal ID.

### OUR SOLUTION

From our auto-install program for terminals, we start our new transaction AUPR. Our auto-install program was built from the

sample auto-install program DFHZATDX. The same transaction is activated from the TOR and the AOR. AUPR decides whether the default printer and/or the override printer need to be defined in this CICS for this terminal.

Printers for CSPK are needed only in the TOR. Virtual terminals (VIRT) from Netpass (session manager) don't have default printer definitions.

We execute a CICS ENQUEUE command on the printer name so that we don't have any conflicts if two terminals needing the same printer should log on at the same time.

An INQUIRE terminal command is executed to determine whether these printers were already defined in the CICS.

Netnames for the printers are read in from a VSAM file containing all the printers. This file is created anew by our VTAM team whenever changes occur in the VTAM definitions. The file contains the four characters of the terminal ID and the eight characters of the netname of all the printers. The file is called AUTOPRNT.

A CICS CREATE command is executed to define the printer. A message is written to the DCT queue CPLI.

This transaction will run in a separate TCLASS to prevent overloads in the morning when everyone signs on or in situations where the computer or CICS fails.

#### AN ALTERNATIVE SOLUTION

Before we implemented the start to AUPR in the terminal auto-install program, we had it running from our sign-on program. One program ran in the TOR and executed all the necessary creates for the TOR. It also had code that started another transaction for all the AORs that had transactions running on printers.

#### RESULTS

In our TOR, the maximum number of printers defined comes to 1,700. In any AOR the maximum number of printers defined comes to 500. We are now also free from the paperwork of defining printers.

## SOURCE CODE

In our auto-install terminal program, the following code was added.  
Add the following data definitions:

```
DFHEISTG DSECT ,
USER_NETNAME DS CL8
USER_MSG     DS CL120
```

The following code is added in the auto-install section for the TOR:

```
      LH  R6,NETNAME_LENGTH  PICK UP NETNAME LENGTH
      LA  R7,8                SET LENGTH FOR COMPARE
      CR  R6,R7              NETNAME LONGER THAN 8 CHARS?
      BNH NETNMOVE          ...NO, MOVE FIRST N CHARS
      MVC USER_NETNAME(8),NETNAME
      B   STRTTRAN          START TRAN FOR PRINTER AUTOINSTALL
NETNMOVE BCTR R6,R0         LENGTH-1 ==> R6
      MVC USER_NETNAME,=CL8' '
      EX  R6,NETNMVC        SELECT NETNAME
      B   STRTTRAN          START TRAN FOR PRINTER AUTOINSTALL
*
NETNMVC MVC  USER_NETNAME(0),NETNAME  EXECUTE MOVE
MSG1    DC CL120'SYAUPR41:START TRAN FOR PRINTER AUTOINSTALL FAILED'
*
STRTTRAN EXEC CICS START TRANSID('AUPR')
           FROM(USER_NETNAME)
           LENGTH(L'USER_NETNAME)
           NOHANDLE
      CLC  EIBRESP,DFHRESP(NORMAL)
      BE  RETURN
      MVC  USER_MSG,MSG1
      EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(USER_MSG) NOHANDLE
```

The following code is added in the section called function seven for  
install to shipped terminals:

```
      MVC  USER_NETNAME,=CL8' '
      L    R8,INSTALL_SHIPPED_NETNAME_PTR
      MVC  USER_NETNAME,0(R8)
      EXEC CICS START TRANSID('AUPR')
           FROM(USER_NETNAME)
           LENGTH(L'USER_NETNAME)
           NOHANDLE
      CLC  EIBRESP,DFHRESP(NORMAL)
      BE  RETURN
      MVC  USER_MSG,MSG2
      EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(USER_MSG) NOHANDLE
      B    RETURN          EXIT PROGRAM
MSG2    DC CL120'SYAUPR41:START TRAN FOR SHIPPED AUTOINSTALL FAILED'
```

## This is the code for the AUPR transaction:

```
AUPRNTR: PROC(CA_PTR) OPTIONS(MAIN);
DCL PLIXOPT CHAR(28) VAR STATIC EXTERNAL
      INIT('ISASIZE(3500) NOSTAE');

/* TRAN: AUPR      PROGRAM: AUPRTOR      */
/* DESCRIPTION:   PROCESS FOR AUTOINSTALL FOR PRINTERS */
/*              AS TERMINALS LOG ON TO CICS.          */
/*-----*/
/*----- */
/* GET COMMON AREA */
/*----- */
DCL 1 GETNET,
      2 GETCOMM          CHAR(4),
      2 GETREM           CHAR(4),
/*-----*/
/* SPRN RECORD */
/*-----*/
      SPRNPRNT          CHAR(80),
      SPRNTERM          CHAR(4),
/*-----*/
/* WORKING AREA */
/*-----*/
      (SUBSTR,ADDR)     BUILTIN,
      DEFPRINT(2)       CHAR(4),
      ACQ                FIXED BIN(31),
      ATLEN              FIXED BIN(15),
      ATTRB              CHAR(39),
      AUTO80             CHAR(80),
      CA_PTR             PTR,
      YESSPRN            FIXED BIN(15),
      KEYTERM            CHAR(4),
      MSGHELLO           CHAR(100),
      NETNM              CHAR(8),
      RESPCODE           FIXED BIN(31),
      SYSIDNM            CHAR(4),
      1 TIME,
      2 FIL1             CHAR(1),
      2 HH               CHAR(2),
      2 FIL2             CHAR(1) INIT(':'),
      2 MM               CHAR(2),
      2 FIL3             CHAR(1) INIT(':'),
      2 SS               CHAR(2),
      TIMESTR           BASED(ADDR(TIME)) CHAR(9),
      1 TIMEPIC,
      2 NULL             PIC '9',
      2 HH               PIC '99',
      2 MM               PIC '99',
      2 SS               PIC '99',
```

```

    TIMESTR2  BASED(ADDR(TIMEPIC)) PIC '(7)9',
    NOVIRT          FIXED BIN(15),
    DECLEND        CHAR(11) INIT('END DECLARE');
/*-----*/
/*  INITIALIZATION */
/*-----*/
    TIMESTR2 = EIBTIME;
    TIME.HH = TIMEPIC.HH;
    TIME.MM = TIMEPIC.MM;
    TIME.SS = TIMEPIC.SS;
    DEFPRINT(1) = '    ';
    DEFPRINT(2) = '    ';
/*-----*/
/*  RECEIVE COMMON AREA */
/*-----*/
    EXEC CICS RETRIEVE INTO(GETNET);
/*-----*/
/*  CHECK IF TERMINAL IS FROM NETPASS */
/*-----*/
    NOVIRT = 1;
    IF GETCOMM = 'VIRT' THEN NOVIRT = 2;
/*-----*/
/*  BUILD DEFAULT PRINTER NAME */
/*-----*/
    DEFPRINT(1) = SUBSTR(GETCOMM,1,3)||'2';

/*-----*/
/*  CHECK SPRN(FOR CSPK) FILE ONLY IN TOR */
/*-----*/
    YESSPRN = 1;
    EXEC CICS ASSIGN SYSID(SYSIDNM);
    IF SUBSTR(SYSIDNM,4,1) = 'A'
        THEN DO;
        EXEC CICS READ FILE('SYPVPRNT') INTO(SPRNPRNT) RIDFLD(GETCOMM)
            RESP(RESPCODE) NOHANDLE;
        SPRNTERM = SUBSTR(SPRNPRNT,5,4);
        IF DFHRESP(NORMAL) = RESPCODE THEN DO;
            YESSPRN = 2;
            DEFPRINT(2) = SPRNTERM;
        END;
    ELSE DO;
        IF DFHRESP(DISABLED) = RESPCODE |
            DFHRESP(NOTOPEN) = RESPCODE |
            DFHRESP(FILENOTFOUND) = RESPCODE
        THEN DO;
            MSGHELLO = 'AUPRTOR -'|| TIMESTR ||
                ' SPRN FILE ERROR  ';
            EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
        END;
        IF DFHRESP(NOTFND) = RESPCODE
        THEN DO;

```

```

        MSGHELLO = 'AUPRTOR -' || TIMESTR ||
        ' SPRN UNKNOWN ERROR/ RESPCODE =' || RESPCODE;
        EXEC CICS WRITEQ TD QUEUE('CSSL') FROM(MSGHELLO);
        END;
    END;
END;
/*-----*/
/* DO THIS STEP 1 OR 2 TIMES DEPENDING */
/* ON WHETHER AN ENTRY WAS FOUND IN SPRN.*/
/*-----*/
DO I = NOVIRT TO YESSPRN;
/*----- */
/* CHECK IF PRINTER IS DEFINED */
/*----- */
KEYTERM = DEFPRINT(I);
EXEC CICS ENQ RESOURCE(KEYTERM) LENGTH(4);
EXEC CICS INQUIRE TERMINAL(KEYTERM) ACQSTATUS(ACQ)
        RESP(RESPCODE) NOHANDLE;
IF DFHRESP(NORMAL) = RESPCODE THEN DO;
    MSGHELLO = 'AUPRTOR -' || TIMESTR || ' REQUEST FROM ' ||
        GETCOMM || ' UNNECESSARY ' ||
        KEYTERM || ' ALREADY DEFINED';
    EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
    GO TO SKIPTURN;
END;
IF DFHRESP(TERMIDERR) = RESPCODE THEN DO;
    MSGHELLO = 'AUPRTOR -' || TIMESTR ||
        ' RESPCODE = ' || RESPCODE || ' FOR PRINTER '
        || KEYTERM || ' FROM TERMINAL ' || GETCOMM;
    EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
    GO TO SKIPTURN;
END;
ELSE DO;
/*-----*/
/* GET NETNAME FROM VTAM FILE */
/*-----*/
NETNM = ' ';
EXEC CICS READ FILE('AUTOPRNT') INTO(AUTO080) RIDFLD(KEYTERM)
        RESP(RESPCODE) NOHANDLE;
IF DFHRESP(NOTOPEN) = RESPCODE |
    DFHRESP(FILENOTFOUND) = RESPCODE THEN DO;
    MSGHELLO = 'AUPRTOR -' || TIMESTR ||
        ' AUTOPRNT FILE NOT READABLE <—';
    EXEC CICS WRITEQ TD QUEUE('CSSL') FROM(MSGHELLO);
    MSGHELLO = 'AUPRTOR -' || TIMESTR ||
        ' AUTOPRNT FILE NOT READABLE <—';
    EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
    GO TO LEAVE;
END;
ELSE IF DFHRESP(DUPKEY) = RESPCODE |
    DFHRESP(NOTFND) = RESPCODE THEN DO;
    MSGHELLO = 'AUPRTOR -' || TIMESTR ||

```



```

        ' NETNAME NOT FOUND FOR PRINTER ' ||
        KEYTERM || ' FROM TERMINAL ' || GETCOMM;
EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
GO TO SKIPTURN;
END;
ELSE DO;
    NETNM = SUBSTR(AUT080,1,8);
    END;
/*-----*/
/*   CREATE PRINTER   */
/*-----*/
ATTRB = 'NETNAME('||NETNM||
        ') TYPETERM(LU3000)';
ATLEN = 34;
EXEC CICS CREATE TERMINAL(KEYTERM)
        ATTRIBUTES(ATTRB) ATTRLEN(ATLEN)
        RESP(RESPCODE) NOHANDLE;
IF DFHRESP(NORMAL) = RESPCODE THEN DO;
    MSGHELLO = 'AUPRTOR -'|| Timestr ||
        ' ' || KEYTERM ||
        ' SUCCESSFULLY CREATED FOR ' || GETCOMM;
EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
END;
ELSE DO;
    MSGHELLO = 'AUPRTOR -'|| Timestr ||
        ' '||KEYTERM||
        ' NOT CREATED,RESPCODE = '||
        RESPCODE || ' FOR ' || GETCOMM;
EXEC CICS WRITEQ TD QUEUE('CPLI') FROM(MSGHELLO);
END;
END; /* END OF ELSE DO; */
SKIPTURN:
EXEC CICS DEQ RESOURCE(KEYTERM) LENGTH(4);
END; /* END OF DO LOOP FOR 2 POSSIBLE PRINTERS */
LEAVE:
EXEC CICS RETURN;
END AUPRNTR;
/*
//LKED.SYSLMOD DD DSN=CICS.LOADSYS,DISP=SHR
//LKED.SYSIN DD *
        NAME AUPRNTR(R)
/*

```

## MESSAGES

The following are samples of the DCT messages that are written.

Terminal JFI4 logs on:

```
DFHZC5966 I 99/03/17 06:26:35 CICSPROD INSTALL STARTED FOR
```

```
TERMINAL ( JFI4 ) SYSID (CPRD) (MODULE : DFHBSTZ ).
DFHZC6935 I 99/03/17 06:26:35 CICSProd AUTOINSTALL FOR
TERMINAL JFI4 WITH NETNAME JFI4P3E0 USING MODEL OR TEMPLATE
TYPLU22 SUCCESSFUL.
```

As a result of JFI4 logging on, AUPRNTR started to run and installed the printer JFI2:

```
DFHZC5966 I 99/03/17 06:26:35 CICSProd INSTALL STARTED FOR
TERMINAL ( JFI2 ) SYSID (CPRD) (MODULE : DFHBSTZ ).
???? ??? AUPR S03 99.076 06.26.35 CREATE TERMINAL(JFI2)...
AUTINSTMODE PRINTERCOPY(NO) ALTPRINTCOPY(NO)...
TERMPRIORITY(0) INSERVICE(YES) AT
AUPRNTR - 06:26:35 JFI2 SUCCESSFULLY CREATED FOR JFI4
```

JFI1 logs on:

```
DFHZC5966 I 99/03/17 06:27:36 CICSProd INSTALL STARTED FOR
TERMINAL ( JFI1 ) SYSID (CPRD) (MODULE : DFHBSTZ ).
DFHZC6935 I 99/03/17 06:27:36 CICSProd AUTOINSTALL FOR TERMINAL JFI1
TYPLU22 SUCCESSFUL.
```

As a result of JFI1 logging on, AUPRNTR started to run but the printer JFI2 was already defined:

```
AUPRNTR - 06:27:36 REQUEST FROM JFI1 UNNECESSARY JFI2 ALREADY DEFINED
```

---

*Sandra Ben Dov, Nadav Tarshish, and Vitaly Miliavsky*  
*Israel National Insurance Institute (Israel)*

© Xephon 1999

---

## Analysing DSNC abends

The following article is based on COBOL II, CICS/ESA 4.1, and DB2 Version 5. Although field offsets can change from release to release, the basic method should also work with releases other than those mentioned.

Under certain circumstances, DB2 abends a CICS task and a DSNC dump is taken. This article will help you to find out the reason for the abend and also find which SQL statement caused the error. You can find the abending program and statement even when you have some COBOL programs statically linked together.

## FINDING THE CAUSE OF THE ABEND

To find the cause of the abend, the first task is to find the DB2 Reason Code. This code is contained in the structure CLOT. You can find a description of the CLOT in member DSNWCBDS in the DB2 sample library.

If you have the internal trace running, the CLOT is easy to find by searching the second 'AP01C0' trace entry (the default trace ID, if this is not changed in the RCT). This contains the actual CLOT in the seventh parameter, as shown in Figure 1. Note that the trace shown in Figure 1 is truncated.

In the text form, which is not shown here, the seventh parameter starts with the eyecatcher DSN2LOT. The trace will always contain the seventh parameter when an exception has occurred. If you always want to have the DSN2LOT contained in the trace, you must ensure that you have defined trace level two for the FC component (for further information, see the *Changes to Database Management* section of the *CICS/ESA Release Guide*).

Now, in offset X'64', you will find a 4-byte hex value, which is the so-called 'Work Word One' or 'Reason Code'. Taking this message

```
AP 01C0 USER  EVENT - USER-EXIT-PROGRAM-ENTRY

TASK-00151 KE_NUM-005C TCB-009C5D90 RET-8DB44B92 TIME-17:37:44.1090718125 INTERVAL
1-0000 C4C2F240 60405CC5 E7C35C
2-0000 C9D5D8D8 80008424
3-0000 C4C5C6C1 E4D3E340
4-0000 0D7EA09C
5-0000 0EBDFA30
6-0000 0EB58090
7-0000 C4E2D5F2 D3D6E340 000B0000 00020A90 0EBDFA30 0EB58090 E4C3C9C3 E2D6D7D9
0020 40404040 40404040 C9D5D8D8 00000000 00000000 00000000 00000000 C3C8E2C5
0040 C7C1F0F0 E9E3F1E4 C1F0F1F7 CFA26D32 29790000 00810004 80008424 00000000
0060 00000000 00F30034 C9D5D8D8 80008424 0D8001F8 00000000 00000000 00000000
0080 00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000
00A0 C4C5C6C1 E4D3E340 01C00000 00000000 00E4C3C9 C3E2D6D7 D9050484 00000000
00C0 00000000 0000
```

*Figure 1: Example of CLOT*

number (in this case X'00F30034'), you can consult the *DB2 Messages and Codes* manual to find the corresponding explanation.

Another useful field is in offset X'5B', called CLOTCLFLG. This one-byte length field contains further information and is needed when the Reason Code was set to X'00'. Further explanation of the CLOTCLFLG can also be found in the *DB2 Messages and Codes* manual, in the DSNCL section of the appendix *CICS Transaction Abend/Dump Code*.

If the internal trace is not running (or does not contain the seventh parameter for the DSN2LOT), you will have to go through the TIE chain for the failing task, until you find the TIE containing the eyecatcher DSN2LOT in offset X'6C'. Because the CLOT is now embedded in the TIE, the offsets for the Reason Code and for the CLOTCLFLG are now X'D0' and X'C7' respectively.

## FINDING THE FAILING SQL STATEMENT

Sometimes, the failing SQL statement is of interest. This can be found by examining the parameter list, which is passed to DB2. Because I couldn't find any hints on how to do this, I wrote a test program, which I forced to a DSNCL abend. Because I know which SQL statement will fail, I can backtrack the usage of the parameter list. This method seems to be working well.

```
01 SQL-PLIST3.                                BLW=0000+1E8 0CL40
 05 SQL-PLIST-CON    PIC S9(9) COMP-4 VALUE +2621440.    BLW=0000+1E8,0000000 4C
 05 SQL-CALLTYPE    PIC S9(4) COMP-4 VALUE +50.          BLW=0000+1EC,0000004 2C
 05 SQL-PROG-NAME    PIC X(8)          VALUE 'INQUERY'.   BLW=0000+1EE,0000006 8C
 05 SQL-TIMESTAMP-1 PIC S9(9) COMP-4 VALUE +372896824.   BLW=0000+1F6,000000E 4C
 05 SQL-TIMESTAMP-2 PIC S9(9) COMP-4 VALUE +23578896.   BLW=0000+1FA,0000012 4C
 05 SQL-SECTION      PIC S9(4) COMP-4 VALUE +1.          BLW=0000+1FE,0000016 2C
 05 SQL-CODEPTR      PIC S9(9) COMP-4.                   BLW=0000+200,0000018 4C
 05 SQL-VPARMPTR     PIC S9(9) COMP-4 VALUE +0.          BLW=0000+204,000001C 4C
 05 SQL-APARMPTR     PIC S9(9) COMP-4 VALUE +0.          BLW=0000+208,0000020 4C
 05 SQL-STMT-NUM     PIC S9(4) COMP-4 VALUE +202.        BLW=0000+20C,0000024 2C
 05 SQL-STMT-TYPE    PIC S9(4) COMP-4 VALUE +3.          BLW=0000+20E,0000026 2C
```

*Figure 2: SQL Precompiler trace*

```

00000000  00B46EC4 C6C8C5C9 E4E24040 40404040 00000000 00000000 00000000 00000000
00000020  00000000 00000000 00000000 00000000 00000000 00000000 00000000 00000000
00000040  00202E98 40404040 002000D0 80000000 0D7EA21C 00000000 0D800030 0D7EA21C
00000060  8009C798 8D560350 0009C798 0D6BB000 8DB452C4 0D6BB05C 0D79D080 00000000
00000080  0D6BAF30 0D7EA030 00081DAC 8009BCD0 0009CCD0 00058388 00058080 00000000
000000A0  00000000 00200050 00200054 00000000 00000000

```

*Figure 3: First save area in offset X'54'*

For each EXEC SQL, the SQL Precompiler generates a unique structure, which is the first one in the parameter list. It contains several fields, including the DBRM name (contained in the field SQL-PROG-NAME) and the statement number (contained in the field SQL-STMT-NUM) of the related EXEC SQL (see Figure 2).

To find which SQL statement caused the error, we have to go through the save areas until we reach the save area from our program. This is done by starting with the EXEC interface user structure, which contains the first save area at offset X'54'. Figure 3 shows the character display (with the eyecatcher >DFHEIUS truncated).

```

00000000 00201F64 7CF0F0F0 00003FE0 00000208 40000000 *U0000151...000.....* 0D800000
0D800230 00203000 00108001 00201FC0 00000000 8DB44B92 *.....k* 0D800020
0D8001F8 0D800448 0DB44832 0DB443D4 00000000 0DB443D4 *...u...8.....M.....M* 0D800040
0DB44410 0D800260 0DB44660 0DB44400 C3F2E3C7 E34EF4F8 *.....-...C2TGT+48* 0D800060
00202E98 000C219C 0D800238 00000000 0000064D 00000000 *../....q.....(....* 0D800080

```

*Figure 4: Offset X'58'*

At offset X'58', we have the pointer to the save area of our COBOL program (in this case X'0D800030'). Because the save area is part of the so-called TGT, you will also see the eyecatcher C2TGT+48. This is shown in Figure 4, which now has its left side truncated. This is useful for debugging, because it contains the base locators used by COBOL to address the fields in the working storage and linkage section.



# Accessing CEDA from ISPF

## INTRODUCTION

This article provides a facility for issuing any CEDA commands from an ISPF session. The mechanism that makes this possible comes from the IBM CICS Supportpac, CA1D, which can be downloaded free from the IBM CICS Web site (<http://www.software.ibm.com/ts/cics/downloads/>).

This provides two programs, one using the EXCI CALL interface and the other using the LINK interface, that can be called from REXX to execute programs in CICS via the EXCI. This facility uses the LINK interface.

## DESCRIPTION

Commands are entered on an ISPF panel in exactly the same format as would be used if you were using CEDA on CICS. The command is passed in a COMMAREA to program SPGCEDA which then calls DFHEDAP. The outcome of the command is returned in the COMMAREA, then formatted and displayed on the panel.

An EXCI connection is needed in each CICS system in which the facility is to be used and the CICS SDFHEXCI load library is needed on the STEPLIB of the TSO logon PROC.

## CICS CONNECTION AND SESSION DEFINITION

```
DEFINE CONNECTION(REXL) GROUP(TCTREXL)
DESCRIPTION(GENERIC PIPE FOR REXX EXCI)
    ACCESSMETHOD(IRC) PROTOCOL(EXCI) CONNTYPE(GENERIC)
    SINGLESESS(NO) DATASTREAM(USER) RECORDFORMAT(U) QUEUELIMIT(NO)
    MAXQTIME(NO) AUTOCONNECT(NO) INSERVICE(YES) ATTACHSEC(LOCAL)
    BINDSECURITY(NO) USEDFLTUSER(NO)
DEFINE SESSIONS(REXISESS) GROUP(TCTREXL)
DESCRIPTION(SESSIONS FOR SPECIFIC PIPE FOR REXX EXCI)
    CONNECTION(REXL) PROTOCOL(EXCI) MAXIMUM(0,0) RECEIVEPFX($)
    RECEIVECOUNT(10) SENDSIZE(4096) RECEIVESIZE(4096)
    SESSPRIORITY(0) AUTOCONNECT(NO) BUILDCHAIN(YES) USERAREALEN(0)
    IOAREALEN(4096,4096) RELREQ(NO) DISCREQ(NO) NEPCCLASS(0)
    RECOVPTION(SYSDEFAULT)
```

# SPGCEDA

```

*-----*
*
* CALL DFHEDAP (CEDA) PASSING A COMMAND RECEIVED IN THE FIRST 1022
* BYTES OF THE COMMAREA. PASS ANY MESSAGES BACK TO THE CALLER IN THE
* BACK END OF THE COMMAREA. COMMAREA MUST BE 6000 BYTES
*
* DFHEDAP EXPECTS A 5 FULLWORD COMMAREA :-
*
*      WORD      POINTS TO
*      1         COMMAND BUFFER
*      2         COMMAND BUFFER LENGTH
*      3         FLAG BYTE (MUST CONTAIN X'00')
*      4         RESPONSE BUFFER
*      5         RESPONSE BUFFER LENGTH
*
*      USING COMMAREA,R2
COMMAREA DSECT
COMMAND DS CL1022
RESPONSE DS CL4978
COMMALEN EQU *-COMMAREA
*
*      DFHREGS
*
*      DFHEISTG
*
RESP      DS      F           RESP FROM CICS COMMANDS
CEDAPARM DS      5F         PARMS FOR DFHEDAP
*
SPGCEDA  DFHEIENT EIBREG=11,CODEREG=12,DATAREG=13
*
      CLC      EIBCALEN,ENOUGH      ENOUGH COMMAREA?
      BNE     THATS_ALL_FOLKS      NO - GET OUT NOW
      L       R2,DFHEICAP          GET COMMAREA ADDRESS
      LA      R1,COMMAND           GET COMMAND BUFFER ADDRESS
      ST      R1,CEDAPARM          PUT INTO PARM WORD 1
      LA      R1,COMMAND_LENGTH    GET COMMAND BUFFER LENGTH ADDRESS
      ST      R1,CEDAPARM+4        PUT INTO PARM WORD 2
      LA      R1,FLAG              GET FLAG ADDRESS
      ST      R1,CEDAPARM+8        PUT INTO PARM WORD 3
      LA      R1,RESPONSE          GET RESPONSE BUFFER ADDRESS
      ST      R1,CEDAPARM+12       PUT INTO PARM WORD 4
      LA      R1,RESPONSE_LENGTH   GET RESPONSE BUFFER LENGTH ADDRESS
      ST      R1,CEDAPARM+16       PUT INTO PARM WORD 5
      EXEC    CICS
*
*      LINK
*      PROGRAM('DFHEDAP')
*      COMMAREA(CEDAPARM)
*      LENGTH(COMMAREA_LENGTH)
*      RESP(RESP)

```



```

THATS_ALL_FOLKS DS 0H
                EXEC CICS RETURN
*
ENOUGH  DC      AL2(COMMALEN)
COMMAND_LENGTH DC AL2(L'COMMAND)
COMMAREA_LENGTH DC AL2(20)
RESPONSE_LENGTH DC AL2(L'RESPONSE)
*
FLAG    DC      X'00'
*
                END

```

## REXX ROUTINE CEDA

```

/***** REXX *****/
/*
/* Access CEDA from ISPF.
/*
/*****
n1 = X2C("15")
program_name = "SPGCEDA"
address ispexec

/* Clear the normal paging keys so we can do our own */
"VGET (ZPF07,ZPF08,ZPF19,ZPF20)"
hpf07 = zpf07
hpf08 = zpf08
hpf19 = zpf19
hpf20 = zpf20
zpf07 = ""
zpf08 = ""
zpf19 = ""
zpf20 = ""
"VPUT (ZPF07,ZPF08,ZPF19,ZPF20)"

/* LIBDEF ISPLLIB to the library where CA1DLINK lives */
"LIBDEF ISPLLIB DATASET",
  "ID('JSDCIC.SVG.CICSLOAD' 'SYSTAG.#1GA078.CICSLOAD')"

/* Here we go */
"DISPLAY PANEL(CEDA)"
do while rc = 0
  "VGET (RESPONSE) SHARED"

/* Clear the results area */
do i=1 to 14
  interpret "line"i = ''
end
select

```

```

/* ENTER pressed so we need to call SPGCEDA */
  when response = "ENTER" then do
    message = ""
    start_at = 1

/* Prepare to call CA1DLINK */
  cics = STRIP(cics)
  commarea = COPIES(" ",6000)
  commarea_len = LENGTH(commarea)
  parm = "PROGRAM("program_name") COMMAREA(COMMAREA)" ,
        "LENGTH("commarea_len") APPLID("cics)"
  commarea = OVERLAY(cedacmd,commarea)
  CALL CA1DLINK PARM

/* Check the response from CA1DLINK */
  response = RIGHT(commarea,4978)
  length = C2D(SUBSTR(response,1,2))
  count = C2D(SUBSTR(response,3,2))
  severity = C2D(SUBSTR(response,5,2))
  sev1 = severity
  if severity > 4 then do
    rest = STRIP(SUBSTR(response,8))
    parse var rest message (NL) rest
  end

/* Get the lines of output from the buffer */
  out_length = C2D(SUBSTR(response,length+1,2))
  out_count = C2D(SUBSTR(response,length+3,2))
  out_severity = C2D(SUBSTR(response,length+5,2))
  sev2 = out_severity
  rest = STRIP(SUBSTR(response,length+8))
  line. = ""
  lines = 0
  parse var rest line (NL) rest
  do while rest ""
    lines = lines + 1
    line.lines = STRIP(line)
    parse var rest line (NL) rest
  end
  if line "" then do
    lines = lines + 1
    line.lines = STRIP(line)
  end
  call BUILD_SCREEN
end

/* Page up */
  when response = "UP" then do
    if start_at - 14 > 0 then start_at = start_at - 14
    call BUILD_SCREEN

```

```

        end

/* Page down */
    when response = "DOWN" then do
        if start_at + 14 <= lines then start_at = start_at + 14
        call BUILD_SCREEN
        end
        otherwise nop
    end
    "DISPLAY PANEL(CEDA)"
end
"LIBDEF ISPLLIB"

/* Restore the normal paging keys */
zpf07 = hpf07
zpf08 = hpf08
zpf19 = hpf19
zpf20 = hpf20
"VPUT (ZPF07,ZPF08,ZPF19,ZPF20)"
exit

/* Build the results screen */
BUILD_SCREEN:
j = 1
do i=start_at to start_at + 13
    if line.i = "" then leave i
    interpret "line"j" = line.i"
    j = j + 1
end
message = "Stage 1 rc = "sev1", stage 2 rc = "sev2"
return

```

## PANEL CEDA

```

)Attr Default(%+_)
% TYPE(TEXT ) INTENS(HIGH) COLOR(YELLOW)
+ TYPE(TEXT ) INTENS(LOW ) COLOR(TURQUOISE)
_ TYPE(INPUT) INTENS(HIGH) CAPS(ON ) JUST(LEFT ) COLOR(GREEN)
! type(input) intens(high) caps(on ) just(left ) pad('.') COLOR(GREEN)
# type(output) intens(low ) caps(off) just(asis ) COLOR(green)
@ type(output) intens(low ) caps(off) just(asis ) COLOR(red)
)Body Expand(//)
%-/-/- CEDA -/-/-
%Command ==>_zcmd
%
+CICS system : !cics +
+CEDA Command : _cedacmd
+/-/-/-

```

```

#line1
#line2
#line3
#line4
#line5
#line6
#line7
#line8
#line9
#line10
#line11
#line12
#line13
#line14
+ - / - / -
@message
)Init
)Proc
&response = &Z
if (.RESP = END)
    &response = 'END'
if (.RESP = ENTER)
    &response = 'ENTER'
if (.PFKEY = PF07)
    &response = 'UP'
if (.PFKEY = PF19)
    &response = 'UP'
if (.PFKEY = PF08)
    &response = 'DOWN'
if (.PFKEY = PF20)
    &response = 'DOWN'
VPUT (RESPONSE) SHARED
)End

```

## JCL CHECKER

```

/*----- REXX -----*/
/*
/* Routine that will check JCL. Actually JES does the syntax
/* checking, we just make sure that datasets exist etc.
/* JCL to to be checked is read from DD JCL and a report is
/* produced at DD REPORT
/*
/* Sample JCL :-
/*
/* //JBSP27XX JOB .....
/* //CICSPARM EXEC PGM=IKJEFT01,
/* //          PARM='%JCLSCAN'
/* //SYSEXEC DD DSN=<exec library>,DISP=SHR
/* //SYSTSPRT DD SYSOUT=*

```

```

/* //SYSTSIN DD DUMMY */
/* //JCL DD DSN=<dataset>(member),DISP=SHR */
/* //REPORT DD SYSOUT=* */
/* */

arg debug

if debug = "TRACE" then trace r

"PROFILE MSGID"
userid = USERID()

/*-----*/
/* Get the name of the dataset we're processing */
/*-----*/
rc = OUTTRAP("INFO.", "*", "CONCAT")
"LISTA STATUS"
rc = OUTTRAP("OFF")

do i=1 to info.0
  if POS("-DDNAME-DISP-",info.i) > 0 then iterate
  if POS("NULLFILE",info.i) > 0 then iterate
  if POS("TERMFILE",info.i) > 0 then iterate
  jcl_dsname = STRIP(info.i)
  j = i+1
  parse var info.j ddname .
  ddname = STRIP(ddname)
  if ddname = "JCL" then leave
  i = j
end

parse var jcl_dsname . "(" jcl_member ")" .

/*-----*/
/* Read the job */
/*-----*/
"EXECIO * DISKR JCL (STEM LINE. FINIS)"

/*-----*/
/* Find out if it's a JOB or an STC */
/*-----*/

its_a_job = 0
do i=1 to line.0
  if LEFT(line.i,3) = "/*" then iterate
  if POS(" JOB ",line.i) > 0 then its_a_job = 1
  leave
end

/*-----*/
/* If it's a job then modify its job card to make sure it's got */

```



```

    queue "//*"
    queue "/"jcl_member" EXEC "jcl_member
end
queue "GO"

/*-----*/
/* Submit the job and get its job-id */
/*-----*/

x = OUTTRAP("LINE.", "*", "CONCAT")
address TSO "SUBMIT * END(GO)"
x = OUTTRAP("OFF")
do i = 1 to line.Ø
    if POS("IKJ5625ØI", line.i) > Ø then do
        parse var line.i . " JOB " jobid .
        leave i
    end
end
end

/*-----*/
/* Wait till the job finishes */
/*-----*/

x = OUTTRAP("LINE.", "*", "CONCAT")
address TSO "STATUS "jobid
x = OUTTRAP("OFF")
parse var line.1 . (jobid) status
do while status ^= "ON OUTPUT QUEUE"
    x = OUTTRAP("LINE.", "*", "CONCAT")
    address TSO "STATUS "jobid
    x = OUTTRAP("OFF")
    parse var line.1 . (jobid) status
end

/*-----*/
/* Get the job from the input queue */
/*-----*/

address TSO "ALLOC F(LISTING) NEW SPACE(2 1) TRACKS"
x = LISTDSI("LISTING" "FILE")
x = OUTTRAP("LINE.", "*", "CONCAT")
address TSO "OUTPUT ("jobid") PRINT('sysdsname')"
x = OUTTRAP("OFF")
address TSO "EXECIO * DISKR LISTING (STEM LINE. FINIS)"
x = MSG("OFF")
address TSO "FREE F(LISTING)"
x = MSG("ON")

/*-----*/
/* See if we had a JCL error. */
/*-----*/

```

```

jcl_err_stmt. = ""
jcl_errs = 0
jcl_error = 0
do i=1 to line.0
  if POS("IEFC452I",line.i) > 0 then do
    do j=i+1 to line.0
      if POS("STMT NO. MESSAGE",line.j) > 0 then do k=j+1 to line.0
        parse var line.k stmt_no msg_id msg
        if (msg_id = "IEFC001I") | (msg_id = "IEFC002I") then iterate
        jcl_errs = jcl_errs + 1
        jcl_err_stmt.jcl_errs = stmt_no
        j = k
      end
    end
  end
  leave i
end
end

/*-----*/
/* Scan for datasets */
/*-----*/
dsname. = ""
line_no. = ""
dsnames = 0
do i=1 to line.0
  if ((POS("//",line.i) > 0) & ,
      (POS("DSN=",line.i) > 0) & ,
      (POS("/*",line.i) = 0)) | ,
      ((POS("XX",line.i) > 0) & ,
      (POS("DSN=",line.i) > 0) & ,
      (POS("XX*",line.i) = 0)) then do
    parse var line.i . "DSN=" dsname "," .
    parse var dsname dsname .
    if POS("&",dsname) = 0 then do
      dsnames = dsnames + 1
      dsname.dsnames = dsname
      line_no.dsnames = i
    end
  else do j=i+1 to line.0
    if POS("IEFC653I",line.j) > 0 then do
      parse var line.j . "DSN=" dsname "," .
      if dsname "= " then do
        parse var dsname dsname .
        dsnames = dsnames + 1
        dsname.dsnames = dsname
        line_no.dsnames = j
        i = j
        leave j
      end
    end
  end
end
end

```



```

        end
    end
end

/*-----*/
/* Write the report */
/*-----*/

line_count = 66
out = 0
out_line. = ""
head_1 = "1CICS Team JCL Checker run on "DATE("E")" at "TIME("N")
head_2 = "0Checking "jcl_dsname
head_3 = "0"CENTRE("ERROR MESSAGES",40,"-")
head_3 = head_3" "CENTRE("JES LISTING",80,"-")

no_jcl_yet = 1
jcl_to_do = 0
final_return_code = 0
do i=1 to line.0
    line = SUBSTR(line.i,2)
    if no_jcl_yet then do
        if POS("//",line) > 0 then do
            jcl_to_do = 1
            no_jcl_yet = 0
        end
    end
end
if POS("STMT NO. MESSAGE",line) > 0 then jcl_to_do = 0
msg = COPIES(" ",41)
out_line = msg||line
if jcl_to_do then do
    parse var line stmt_no .
    no_jcl_error = 1
    do j=1 to jcl_errs
        if jcl_err_stmt.j = stmt_no then do
            msg = "!E! JCL ERROR : SEE MESSAGES"
            out_line = OVERLAY(msg,out_line,2,40)
            no_jcl_error = 0
            final_return_code = 8
            leave j
        end
    end
end
if no_jcl_error then do j=1 to dsnames
    if i = line_no.j then do
        msg = SYSDSN(" "dsname.j" ")
        if msg = "OK" then do
            msg = "!E! "msg
            out_line = OVERLAY(msg,out_line,2,40)
            final_return_code = 8
        end
    end
end

```

```

        leave j
    end
end
end
line_count = line_count + 1
if line_count > 56 then do
    out = out + 1
    out_line.out = head_1
    out = out + 1
    out_line.out = head_2
    out = out + 1
    out_line.out = head_3
    out = out + 1
    out_line.out = " "
    line_count = 5
end
out = out + 1
out_line.out = out_line
end

```

```

address TSO "EXECIO * DISKW REPORT (STEM OUT_LINE. FINIS)"
exit final_return_code

```

---

*Kevin Wailes*  
*J Sainsbury (UK)*

© J Sainsbury 1999

---

## CEMT logger – an alternative design

In *A CEMT log for CICS 4.1, CICS Update*, October 1998, Russell Hunt described a system to record CEMT output to the CSMT transient data queue. This consisted of an XZCOUT user exit to capture TIOA output from CEMT commands in a GETMAINED work area, and a COBOL ‘sweeper’ program that periodically writes data from this work area to the CSMT destination.

I have found two problems with this design. Firstly, the user exit program consumes excessive resources, because:

- It executes an (XPI) GETMAIN/FREEMAIN for every invocation of the exit, including those invocations not related to the CEMT transaction.

- It formats the CEMT data before writing it to the buffer. This CPU-intensive processing is better (asynchronously) performed in the 'sweeper' program.

This excessive processing increases the pathlength for all VTAM-related terminal output.

The second problem is that the formatting algorithm for the CEMT data relies on hardcoded displacements of various fields in the output buffer. This makes the algorithm vulnerable to any PTF (or CICS release change) that affects the offset of CEMT output fields.

To overcome these problems, I have redesigned the system. The working storage for the user exit is now obtained once only on the first invocation of the 'sweeper' program (ZZZCEMT). The address of this storage is saved to the GWA of the user exit (ZZZZCOUT). The user exit cannot start processing until this pointer is set. Therefore there is only one GETMAIN per CICS run.

Also, the user exit does no formatting of the CEMT TIOA buffer, but just copies it 'as is' to the work buffer. The user-id is appended to this data as an additional refinement.

Formatting of the CEMT output is now performed by the 'sweeper' program. The formatting algorithm does not rely on hardcoded field offsets, but instead on the presence of the SBA character (X'11') at the start of each new line. This is used as the COBOL UNSTRING delimiter. This technique is unlikely to be affected by future CICS maintenance or release changes. Although COBOL UNSTRING is fairly CPU-intensive, the 'sweeper' transaction only runs every 'n' minutes as a low-priority non-terminal task. The output from the UNSTRING is not 100% neat and tidy, but is adequate for logging purposes.

The 'sweeper' transaction/program is kicked off at PLTPI time. The program then issues an ENABLE EXIT for the XZCOUT user exit, performs a GETMAIN for all working storage, and records the address of this storage in the exit's GWA. It then issues a (self)START after the agreed 'sweeper' interval and terminates. Every subsequent invocation checks the TIOA buffer for data to write to the CSMT TDQ.

Error conditions encountered by the user exit are recorded in the GWA and are written to the CSMT log by the 'sweeper' program. This is a better way to log user exit errors than by using WTO. WTOs always have the potential to flood the MVS console should a loop condition occur.

## ZZZCEMT

```

CBL XOPTS(SP)
CBL TRUNC(OPT) DATA(31)
IDENTIFICATION DIVISION.
PROGRAM-ID.      ZZZCEMT.
*****
*
*FUNCTION: WRITE CEMT RECORDS COLLECTED BY ZZZZCOUT EXIT
*          TO THE 'CSMT' TD QUEUE ('SWEEPER' PROGRAM).
*
*CALLS/LINKS : (NONE)
*
*DESCRIPTION:
*THIS PROGRAM COPIES CEMT OUTPUT RECORDED BY AN XZCOUT GLUE
*PROGRAM TO THE 'CSMT' DCT DESTINATION. THE RECORDS INCLUDE THE
*USER-ID. THIS MAKES IN EFFECT A CEMT LOGGING FACILITY.
*
*THE PROGRAM STARTS AT PLT TIME, ENABLES THE ZZZZCOUT EXIT
*PROGRAM, AND TERMINATES. JUST BEFORE TERMINATION,
*THE PROGRAM ISSUES A START WITH A SUITABLE
*INTERVAL - THE MONITORING INTERVAL - TO RE-ACTIVATE ITSELF.
*
* NOTE - THIS PROGRAM AND ITS ASSOCIATED TRANSACTION MUST RUN IN
* CICS KEY SINCE IT MUST ACCESS THE USER EXIT GWA.
*
*****

ENVIRONMENT DIVISION.
DATA DIVISION.
*****
WORKING-STORAGE SECTION.
*****
Ø1  C-CONSTANTS.
    Ø2  C-EYECATCHER      VALUE '*START OF WORKING STORAGE*'
                                PIC X(26).
    Ø2  C-PROGRAM-ID     VALUE 'ZZZCEMT'          PIC X(8).
    Ø2  C-REQID          VALUE 'ZZZREQ2'         PIC X(8).
    Ø2  C-EXIT-PROGRAM   VALUE 'ZZZZCOUT'       PIC X(8).
    Ø2  C-EXIT-GWALEN    VALUE +91              PIC S9(4) COMP.
    Ø2  C-XZCOUT         VALUE 'XZCOUT'         PIC X(8).

```

```

Ø2 C-VERSION          VALUE 'Ø1.ØØ'          PIC X(5).
Ø2 C-MSG-QUEUE        VALUE 'CSMT'           PIC X(4).
Ø2 C-MONITOR-TRANS-ID VALUE 'ZZZ2'           PIC X(4).
Ø2 C-DEFAULT-INTERVAL-MINS VALUE +2         PIC S9(8) COMP.
Ø2 C-UNDERSCORE       VALUE '_'              PIC X.
Ø2 C-SBA-CHAR         VALUE X'11'            PIC X.
Ø2 C-START-FIELD-CHAR VALUE X'1D'            PIC X.
Ø2 C-INSERT-CURSOR    VALUE X'13'            PIC X.
Ø2 C-WORKAREA-SIZE    VALUE +65536           PIC S9(8) COMP.

Ø1 W-SWITCHES.
Ø2 W-START-CODE       VALUE SPACES           PIC X(2).
   88 SW-START-NO-DATA VALUE 'S '           .
   88 SW-START-WITH-DATA VALUE 'SD'          .
   88 SW-TERMINAL-TASK VALUE 'TD'           .
Ø2 W-PROCESS-SWITCH   VALUE 'N'             PIC X.
   88 SW-NOT-DONE     VALUE 'N'             .
   88 SW-ALL-DONE     VALUE 'Y'             .

Ø1 W-MSG.
Ø2 W-MSG-PROGRAM      PIC X(7).
Ø2 FILLER              VALUE '-'            PIC X.
Ø2 W-MSG-NO           PIC X(2).
Ø2 FILLER              PIC X.
Ø2 W-MSG-TIME         PIC X(8).
Ø2 FILLER              PIC X.
Ø2 W-MSG-TEXT         PIC X(6Ø).

Ø1 W-TIOA-DATA        PIC X(32768).

Ø1 W-WORK-FIELDS.
Ø2 W-EXIT-GWALEN      PIC S9(4) COMP.
Ø2 W-WORK-LENGTH      PIC S9(4) COMP.
Ø2 W-UNSTRING-COUNT   PIC S9(4) COMP.
Ø2 W-WORKAREA-OFFSET  PIC S9(8) COMP.
Ø2 W-TDQ-BUFFER       PIC X(8Ø).
Ø2 W-REQID            PIC X(8).
Ø2 W-PIC5             PIC 9(5).
Ø2 W-GETMAIN-LENGTH   PIC S9(8) COMP.
Ø2 W-INTERVAL-BIN-MINS PIC S9(8) COMP.
Ø2 W-INTERVAL-PIC-MINS PIC 9(2).
Ø2 W-WHEN-COMPILED.
   Ø3 W-COMPILE-DATE   PIC X(8).
   Ø3 W-COMPILE-TIME   PIC X(8).
Ø2 W-ABSTIME          PIC S9(15) COMP.
Ø2 W-RESP             PIC S9(8) COMP.
Ø2 W-RESP2            PIC S9(8) COMP.
Ø2 W-RESP-PIC         PIC 99999.
Ø2 W-RESP2-PIC        PIC 99999.
Ø2 W-WORK-PTR         USAGE IS POINTER.

```

```

Ø2 W-WORK-PTR-BIN REDEFINES W-WORK-PTR      PIC S9(8) COMP.
Ø2 W-WORK-PTR-SAVE                          USAGE IS POINTER.
Ø2 I                                          PIC S9(8) COMP.
Ø2 J                                          PIC S9(8) COMP.
Ø2 K                                          PIC S9(8) COMP.
Ø2 W-CICS-STATUS                            PIC S9(8) COMP.
Ø2 W-DDMMYYYYY                             PIC X(10).
Ø2 W-TIME                                    PIC X(8).

```

```

Ø1 W-CEMT-OUTPUT-TABLE.
  Ø2 W-CEMT-OUTPUT-LINE          OCCURS 100.
    Ø3 W-SBA-ORDERS              PIC X(2).
    Ø3 W-CEMT-OUTPUT-DATA       PIC X(79).

```

```

*****
LINKAGE SECTION.
*****

```

```

Ø1 DFHCOMMAREA                    PIC X(4096).

```

\* GWA DESCRIPTION MUST MATCH DSECT IN ZZZZCOUT

```

Ø1 L-GWA.
  Ø2 L-GWA-DOUBLE-WORD            PIC S9(15) COMP.
  Ø2 L-GWA-WORKAREA1-PTR         USAGE IS POINTER.
  Ø2 L-GWA-WORKAREA2-PTR         USAGE IS POINTER.
  Ø2 L-GWA-OFFSET                PIC S9(8) COMP.
  Ø2 L-GWA-TIOALEN               PIC S9(8) COMP.
  Ø2 L-GWA-TERMID                PIC X(4).
  Ø2 L-GWA-TRANID                PIC X(4).
  Ø2 L-GWA-USERID                PIC X(8).
  Ø2 L-GWA-ERROR-NO              PIC X.
    88 SW-NO-PROBLEMS             VALUE X'00'.
    88 SW-NO-WORKAREA             VALUE X'01'.
    88 SW-XPI-CALL-1-FAILED       VALUE X'02'.
    88 SW-XPI-CALL-2-FAILED       VALUE X'03'.
    88 SW-BUFFER-FULL             VALUE X'04'.
  Ø2 L-GWA-ERROR-MESSAGE         PIC X(49).
  Ø2 L-GWA-STATUS-FLAG           PIC X.
    88 SW-WORKAREA1-ACTIVE        VALUE '1'.
    88 SW-WORKAREA2-ACTIVE        VALUE '2'.

```

```

Ø1 L-WORKAREA.
  Ø2 L-WORKAREA-USERID           PIC X(8).
  Ø2 L-WORKAREA-TERMID          PIC X(4).
  Ø2 L-WORKAREA-TIOALEN         PIC S9(5) COMP-3.
  Ø2 L-WORKAREA-TIOALEN-ALT REDEFINES L-WORKAREA-TIOALEN
                                  PIC X(3).
  Ø2 L-WORKAREA-TIOA-DATA       PIC X(65526).

```

```

*****
PROCEDURE DIVISION.

```

```

*****
*****
0000-MAIN SECTION.
*****
    PERFORM P-INITIALIZE.
    PERFORM P-PROCESS.
    PERFORM P-START-AGAIN.

0000-CICS-RETURN.
    EXEC CICS RETURN NOHANDLE END-EXEC.
    GOBACK.

*****
P-INITIALIZE.
*****
    MOVE SPACES          TO W-MSG.
    MOVE C-PROGRAM-ID    TO W-MSG-PROGRAM.
    MOVE WHEN-COMPILED TO W-WHEN-COMPILED.
    MOVE SPACES          TO W-TDQ-BUFFER.
    MOVE C-DEFAULT-INTERVAL-MINS TO W-INTERVAL-BIN-MINS.
    PERFORM P-GET-TIMESTAMP.
    PERFORM P-CHECK-CICS-STATUS.
    PERFORM P-CHECK-START-MODE.

*****
P-CHECK-CICS-STATUS.
*****
    EXEC CICS INQUIRE SYSTEM
        CICSSTATUS(W-CICS-STATUS)
        RESP(W-RESP)
        RESP2(W-RESP2)
    END-EXEC.

    EVALUATE TRUE
        WHEN W-RESP NOT = DFHRESP(NORMAL)
            MOVE 'INQUIRE SYSTEM ERROR' TO W-MSG-TEXT
            MOVE '01' TO W-MSG-NO
            PERFORM P-HANDLE-ERROR
            GO TO 0000-CICS-RETURN
        WHEN W-CICS-STATUS = DFHVALUE(ACTIVE)
            CONTINUE
        WHEN W-CICS-STATUS = DFHVALUE(STARTUP)
            PERFORM P-PLTPI-PROCESSING
            GO TO 0000-CICS-RETURN
        WHEN OTHER
            MOVE 'CICS IS SHUTTING DOWN' TO W-MSG-TEXT
            MOVE '02' TO W-MSG-NO
            PERFORM P-HANDLE-ERROR
            GO TO 0000-CICS-RETURN

```

END-EVALUATE.

\*\*\*\*\*

P-PLTPI-PROCESSING.

\*\*\*\*\*

PERFORM P-GET-TIMESTAMP.

MOVE WHEN-COMPILED TO W-WHEN-COMPILED.

MOVE C-PROGRAM-ID TO W-MSG-PROGRAM.

MOVE 'ØØ' TO W-MSG-NO.

STRING

'VERSION ' C-VERSION

' COMPILED ' W-COMPILE-DATE ' ' W-COMPILE-TIME

DELIMITED BY SIZE

INTO W-MSG-TEXT

END-STRING.

PERFORM P-WRITE-MSG.

PERFORM P-ENABLE-EXIT-PROGRAM.

PERFORM P-INITIALIZE-EXIT-WORKAREAS.

PERFORM P-START-AGAIN.

\*\*\*\*\*

P-INITIALIZE-EXIT-WORKAREAS.

\*\*\*\*\*

PERFORM P-EXTRACT-EXIT.

IF W-RESP NOT = DFHRESP(NORMAL) THEN

MOVE 'Ø3' TO W-MSG-NO

MOVE 'EXTRACT EXIT FAILED' TO W-MSG-TEXT

PERFORM P-HANDLE-ERROR

GO TO ØØØØ-CICS-RETURN

END-IF.

MOVE +Ø TO L-GWA-OFFSET.

MOVE C-WORKAREA-SIZE TO W-GETMAIN-LENGTH.

PERFORM P-GETMAIN.

SET L-GWA-WORKAREA1-PTR TO W-WORK-PTR.

SET ADDRESS OF L-WORKAREA TO W-WORK-PTR.

MOVE LOW-VALUES TO L-WORKAREA.

MOVE C-WORKAREA-SIZE TO W-GETMAIN-LENGTH.

PERFORM P-GETMAIN.

SET L-GWA-WORKAREA2-PTR TO W-WORK-PTR.

SET ADDRESS OF L-WORKAREA TO W-WORK-PTR.

MOVE LOW-VALUES TO L-WORKAREA.

SET SW-WORKAREA1-ACTIVE TO TRUE.

\*\*\*\*\*



P-EXTRACT-EXIT.

```
*****
EXEC CICS EXTRACT EXIT
      PROGRAM(C-EXIT-PROGRAM)
      GALENGTH(W-EXIT-GWALEN)
      GASET(ADDRESS OF L-GWA)
      RESP(W-RESP)
      RESP2(W-RESP2)
END-EXEC.
```

P-GETMAIN.

```
*****
EXEC CICS GETMAIN
      FLENGTH(W-GETMAIN-LENGTH)
      SET(W-WORK-PTR)
      SHARED
      RESP(W-RESP)
      RESP2(W-RESP2)
END-EXEC.
```

```
IF W-RESP NOT = DFHRESP(NORMAL) THEN
  MOVE '04' TO W-MSG-NO
  MOVE 'GETMAIN FAILED' TO W-MSG-TEXT
  PERFORM P-HANDLE-ERROR
  GO TO 0000-CICS-RETURN
END-IF.
```

P-ENABLE-EXIT-PROGRAM.

```
*****
EXEC CICS ENABLE
      PROGRAM(C-EXIT-PROGRAM)
      ENTRYNAME(C-EXIT-PROGRAM)
      EXIT(C-XZCOUT)
      GALENGTH(C-EXIT-GWALEN)
      START
      RESP(W-RESP)
      RESP2(W-RESP2)
END-EXEC.
```

```
IF W-RESP NOT = DFHRESP(NORMAL) THEN
  MOVE '05' TO W-MSG-NO
  MOVE 'ENABLE EXIT FAILED' TO W-MSG-TEXT
  PERFORM P-HANDLE-ERROR
  GO TO 0000-CICS-RETURN
END-IF.
```

P-CHECK-START-MODE.

```

*****
EXEC CICS ASSIGN
    STARTCODE(W-START-CODE)
    NOHANDLE
END-EXEC.

EVALUATE TRUE
    WHEN SW-START-NO-DATA
        CONTINUE
***** IF TERMINAL TASK, RESTART MONITORING IF IT HAS STOPPED
    WHEN SW-TERMINAL-TASK
        PERFORM P-INQUIRE-REQID
        IF EIBRESP NOT = DFHRESP(NORMAL) THEN
            PERFORM P-EXTRACT-EXIT
            IF EIBRESP NOT = DFHRESP(NORMAL) THEN
                PERFORM P-ENABLE-EXIT-PROGRAM
                PERFORM P-INITIALIZE-EXIT-WORKAREAS
            END-IF
            PERFORM P-START-AGAIN
            MOVE '06' TO W-MSG-NO
            MOVE 'MONITORING RESTARTED' TO W-MSG-TEXT
            PERFORM P-SEND-MSG
            GO TO 0000-CICS-RETURN
        END-IF
    WHEN OTHER
        MOVE '07' TO W-MSG-NO
        MOVE 'INVALID INVOCATION MODE' TO W-MSG-TEXT
        PERFORM P-HANDLE-ERROR
        GO TO 0000-CICS-RETURN
END-EVALUATE.

*****
P-SEND-MSG.
*****
    IF EIBTRMID(1:1) > SPACE THEN
        EXEC CICS SEND CONTROL
            ERASE
            NOHANDLE
        END-EXEC

        EXEC CICS SEND
            FROM(W-MSG)
            LENGTH(LENGTH OF W-MSG)
            NOHANDLE
        END-EXEC
    END-IF.
    MOVE SPACES TO W-MSG-TEXT.

*****
P-PROCESS.

```

```

*****
PERFORM P-EXTRACT-EXIT.

IF W-RESP NOT = DFHRESP(NORMAL) THEN
  MOVE '08' TO W-MSG-NO
  MOVE 'EXTRACT EXIT FAILED' TO W-MSG-TEXT
  PERFORM P-HANDLE-ERROR
  GO TO 0000-CICS-RETURN
END-IF.

EVALUATE TRUE
  WHEN SW-WORKAREA1-ACTIVE
    SET W-WORK-PTR TO L-GWA-WORKAREA1-PTR
    SET SW-WORKAREA2-ACTIVE TO TRUE
  WHEN SW-WORKAREA2-ACTIVE
    SET W-WORK-PTR TO L-GWA-WORKAREA2-PTR
    SET SW-WORKAREA1-ACTIVE TO TRUE
  WHEN OTHER
    MOVE 'NO ACTIVE WORKAREA' TO W-MSG-TEXT
    MOVE '09' TO W-MSG-NO
    PERFORM P-HANDLE-ERROR
    GO TO 0000-CICS-RETURN
END-EVALUATE.

MOVE +0 TO L-GWA-OFFSET.
SET ADDRESS OF L-WORKAREA TO W-WORK-PTR.
SET W-WORK-PTR-SAVE      TO W-WORK-PTR.

PERFORM P-CHECK-FOR-EXIT-ERROR.
**** EXIT IF NOTHING TO COPY
IF L-WORKAREA-USERID = LOW-VALUES THEN
  PERFORM P-START-AGAIN
  GO TO 0000-CICS-RETURN
END-IF.

SET SW-NOT-DONE TO TRUE.
MOVE +0 TO W-WORKAREA-OFFSET.
PERFORM P-WRITE-CEMT-DATA UNTIL SW-ALL-DONE.
SET ADDRESS OF L-WORKAREA TO W-WORK-PTR-SAVE.
MOVE LOW-VALUES TO L-WORKAREA.

*****
P-CHECK-FOR-EXIT-ERROR.
*****
IF NOT SW-NO-PROBLEMS OR
  L-GWA-ERROR-MESSAGE NOT = LOW-VALUES THEN
  MOVE SPACES TO W-TDQ-BUFFER
  STRING
    'ZZZCEMT-99 ERROR IN ZZZZCOUT: ' DELIMITED BY SIZE
    L-GWA-ERROR-MESSAGE             DELIMITED BY ' '

```

```

        INTO W-TDQ-BUFFER
    END-STRING
    PERFORM P-WRITE-TDQ
    MOVE LOW-VALUES TO L-GWA-ERROR-MESSAGE
    SET SW-NO-PROBLEMS TO TRUE
END-IF.

```

\*\*\*\*\*

P-WRITE-CEMT-DATA.

\*\*\*\*\*

```

    IF L-WORKAREA-USERID = LOW-VALUES OR
       L-WORKAREA-TIOALEN-ALT = LOW-VALUES OR
       L-WORKAREA-TIOALEN IS NOT NUMERIC THEN
        SET SW-ALL-DONE TO TRUE
    ELSE
        MOVE L-WORKAREA-TIOALEN TO W-WORK-LENGTH
        STRING
            '** CEMT LOG '
            'USER='   L-WORKAREA-USERID ' '
            'TERMID=' L-WORKAREA-TERMID
        DELIMITED BY SIZE INTO W-TDQ-BUFFER
        END-STRING
        PERFORM P-WRITE-TDQ
        IF W-WORK-LENGTH < +1 THEN
            SET SW-ALL-DONE TO TRUE
        ELSE
            COMPUTE W-WORKAREA-OFFSET = W-WORKAREA-OFFSET +
                                         LENGTH OF L-WORKAREA-TIOALEN +
                                         LENGTH OF L-WORKAREA-USERID +
                                         LENGTH OF L-WORKAREA-TERMID +
                                         W-WORK-LENGTH
            IF W-WORKAREA-OFFSET > C-WORKAREA-SIZE THEN
                SET SW-ALL-DONE TO TRUE
            ELSE
                PERFORM P-PARSE-CEMT-OUTPUT
                ADD W-WORKAREA-OFFSET TO W-WORK-PTR-BIN
                SET ADDRESS OF L-WORKAREA TO W-WORK-PTR
            END-IF
        END-IF
    END-IF.
END-IF.

```

*Editor's note: this article will be concluded next month.*

---

*David Roth*  
*CICS Consultant (Germany)*

© Xephon 1999

---

## Dealing with program abends – part 2

*This month we conclude the program that gets control whenever CICS detects a program abend and displays the transaction ID under which the program was running, along with the abending program name.*

### DPWIZM – WIZARD MAIL INTERFACE PROGRAM

DPWIZM sends WIZMAIL messages to Wizard Mail using DPL, and was written to eliminate the ‘ATNI’ abend caused by DFHPEP. This abend occurred when the code below (formerly contained in DFHPEP) was executed, because DFHPEP executes under an abend state.

```
GBLC  &ABOV
      GBLC  &SYID
&ABOV  SETC  'Y'           SET TO 'N' IF YOU WANT 24-BIT USAGE.
&SYID  SETC  'DEVM'       SET TO SYSID OF WHERE WIZMAIL LIVES.
```

You should assemble and LNKEDT this program as you would any other Assembler CICS command-level program. There are two generation options, specified in the ‘&ABOV SETC ‘Y’ and the ‘&SYID SETC ‘ ’ shown above. You may wish to change these before assembly/LNKEDT:

- If you don’t wish to run this program above the line (ie in 31-bit mode) or if you aren’t using high-level Assembler (ie ASMA90), specify ‘&ABOV SETC N’.
- If you’re running in an MRO/ISC environment and Wizard Mail is running in the TOR, you must specify the four-character SYSID of the CICS system where Wizard Mail is running by entering it in the ‘&SYID SETC ????’ statement. Otherwise, set this option to blank. Note that the value specified in this option is not checked. If an incorrect SYSID is given, an error will occur at program execution time.

Note that:

- The assembly and LNKEDT of this program should end with a \$SRC of zero. If the \$SRC value is different, you should examine the assembly listing, determine the problem, fix it, and reassemble

the program. Note that if you specify any value other than 'Y' or 'N' in the '&ABOV SETC '?' statement, you will receive a \$SRC value of four.

- Before you assemble/LNKEDT this program, you must assemble and catalogue the DPEIBC subroutine (see below), which is called by this program. The subroutine must be catalogued as an .OBJ MEMBERTYPE. The LIB.SUBLIB into which the subroutine is catalogued must be LIBDEFed when you assemble and catalogue this program.
- It doesn't matter which LIB.SUBLIB this program is catalogued into, although it should be one of your own and not an IBM one. The LIB.SUBLIB into which you catalogue the program must be LIBDEFed in your CICS start-up JCL.
- This program requires no special PCT or PPT operands. An RDO sample of the PCT/PPT operands is shown below (note that you should replace the question marks with values of your choice):

```
PCT DEFINITION:
TRANSACTION      : DPWI
GROUP           : ????????
PROGRAM         ==> DPWIZM
TWSIZE          ==> 000000
PROFILE         ==> DFHCICST
PARTITIONSET    ==>
STATUS          ==> ENABLED
PRIMESIZE       ==> 000000
REMOTE ATTRIBUTES
DYNAMIC         ==> NO
REMOTESYSTEM    ==>
REMOTENAME      ==>
TRPROF          ==>
LOCALQ          ==>
SCHEDULING
PRIORITY        ==> ???
TCLASS          ==> NO
ALIASES
ALIAS           ==>
TASKREQ         ==>
XTRANID         ==>
RECOVERY
DTIMOUT         ==> NO
INDOUBT         ==> BACKOUT
RESTART         ==> NO
```

```

SPURGE      ==> ??? (RECOMMEND YES)
TPURGE      ==> ??? (RECOMMEND YES)
DUMP        ==> YES
TRACE       ==> YES
SECURITY
EXTSEC      ==> NO
TRANSEC     ==> 01
RSL         ==> ??? (RECOMMEND PUBLIC)
RSLC        ==> NO

```

PPT DEFINITION:

```

PROGRAM      : DPWIZM
GROUP       : ??
LANGUAGE     ==> ASSEMBLER
RELOAD      ==> NO
RESIDENT    ==> NO
RSL         ==> ??? (RECOMMEND PUBLIC)
STATUS      ==> ENABLED
REMOTE ATTRIBUTES
REMOTESYSTEM ==>
REMOTENAME  ==>
TRANSID     ==>
EXECUTIONSET ==> FULLAPI

```

## DPWIZM

```

DPWI      TITLE 'DPWIZM - 1.0 - WIZARD MAIL INTERFACE PROGRAM.'
          AIF  ('&ABOV' EQ 'Y').ABOV00
          AIF  ('&ABOV' EQ 'N').ABOV00
          MNOTE 4, 'VALUE FOR ''ABOV'' NOT ''Y'' OR ''N'', FORCED TO ''Y''X
          ' . '
&ABOV    SETC  'Y'
.ABOV00  ANOP
DFHEISTG DSECT
RESP     DS    F           RESPONSE CODE. (FROM EXEC CICS COMMA
RETLEN   DS    H           RETRIEVE LENGTH.
APPLID   DS    CL8        APPLID.
STRTCDC  DS    CL2        START CODE.
*
          DFHREGS ,        USE CICS REGISTER EQUATES.
*
          USING WIZCOMM,R9
WIZCOMM  DSECT           WIZARD MAIL DSECT.
          DS    0CL1500
WIZERRM  DS    CL60      WIZMAIL MESSAGE HEADER.
WIZSUBJ  DS    CL25      WIZMAIL MESSAGE SUBJECT.
WIZCONF  DS    C         WIZMAIL CONFIRMATION CODE.
WIZDIS1  DS    CL70      WIZMAIL DISTRIBUTION LINE ONE (1).
WIZDIS2  DS    CL70      WIZMAIL DISTRIBUTION LINE TWO (2).
WIZDIS3  DS    CL70      WIZMAIL DISTRIBUTION LINE THREE (3).

```

WIZDIS4	DS	CL70	WIZMAIL DISTRIBUTION LINE FOUR (4).
WIZMSG1	DS	CL70	WIZMAIL MESSAGE LINE ONE (1).
WIZMSG2	DS	CL70	WIZMAIL MESSAGE LINE TWO (2).
WIZMSG3	DS	CL70	WIZMAIL MESSAGE LINE THREE (3).
WIZMSG4	DS	CL70	WIZMAIL MESSAGE LINE FOUR (4).
WIZMSG5	DS	CL70	WIZMAIL MESSAGE LINE FIVE (5).
WIZMSG6	DS	CL70	WIZMAIL MESSAGE LINE SIX (6).
WIZMSG7	DS	CL70	WIZMAIL MESSAGE LINE SEVEN (7).
WIZMSG8	DS	CL70	WIZMAIL MESSAGE LINE EIGHT (8).
WIZMSG9	DS	CL70	WIZMAIL MESSAGE LINE NINE (9).
WIZMSGA	DS	CL70	WIZMAIL MESSAGE LINE TEN (10).
WIZMSGB	DS	CL70	WIZMAIL MESSAGE LINE ELEVEN (11).
WIZMSGC	DS	CL70	WIZMAIL MESSAGE LINE TWELVE (12).
WIZMSGD	DS	CL70	WIZMAIL MESSAGE LINE THIRTEEN (13).
WIZMSGE	DS	CL70	WIZMAIL MESSAGE LINE FOURTEEN (14).
WIZMSGF	DS	CL70	WIZMAIL MESSAGE LINE FIFTEEN (15).
WIZOPID	DS	CL8	WIZMAIL ORIGINATING OPERATOR ID.
	DS	CL76	NOT USED.

\*

```

DPWIZM  DFHEIENT CODEREG=(RA),DATAREG=(R6),EIBREG=(R4)
        AIF ('&ABOV' NE 'Y').ABOV01
DPWIZM  AMODE 31
DPWIZM  RMODE ANY
.ABOV01 ANOP
MVC     WRTAREA,WRTAREA-1  CLEAR WRTAREA.
MVC     RETLEN,=H'1500'    SET RETRIEVE LENGTH.
EXEC    CICS ASSIGN STARTCODE(STRTCD) APPLID(APPLID)           X
        RESP(RESP).      GET SOME INFORMATION.
CLC     RESP,DFHRESP(NORMAL) WAS THERE AN ERROR.
BE      START              NO-BRANCH TO START.
MVC     WRTAREA(30),=C'DPWIZM-ASSIGN ERROR.
BAL     RB,ERROR3          PERFORM ERROR3 ROUTINE.
B       RETURN            BRANCH TO RETURN.

```

\*

```

START   EQU *
        CLC =C'S ',STRTCD    WERE WE STARTED WITHOUT DATA.
        BNE START3          NO-BRANCH TO START3.
        MVC WRTAREA(30),=C'DPWIZM-START W/NO DATA ERROR '
        BAL RB,WTOC          PERFORM WTOC ROUTINE.
        B   RETURN          BRANCH TO RETURN.

```

\*

```

START3  EQU *
        CLC =C'SD',STRTCD    WERE WE STARTED WITH DATA.
        BNE LINKED          NO-BRANCH TO LINKED.
        EXEC CICS RETRIEVE SET(R9) LENGTH(RETLEN).
        CLC RESP,DFHRESP(NORMAL) WAS THERE AN ERROR.
        BE   RETRVE          NO-BRANCH TO RETRVE.
        MVC WRTAREA(30),=C'DPWIZM-RETRIEVE ERROR.
        BAL RB,ERROR3        PERFORM ERROR3 ROUTINE.
        B   RETURN          BRANCH TO RETURN.

```



```

*
RETRVE EQU *
      CLC  =H'1500',RETLEN      WAS RETRIEVE LENGTH 1500.
      BE   RETRVE2              YES-BRANCH TO RETRVE2.
      MVC  WRTAREA(30),=C'DPWIZM-RETRIEVE LENGTH ERROR. '
      BAL  RB,WTOC              PERFORM WTOC ROUTINE.
      B    RETURN              BRANCH TO RETURN.

*
RETRVE2 EQU *
*      CLC  =C'CICSPRD2',APPLID ARE WE RUNNING IN CICSPRD2.
*      BNE  RETRVE3              NO-BRANCH TO RETRVE3.
*      EXEC CICS LINK PROGRAM('WMPAIM1') COMMAREA(WIZCOMM)          X
*          LENGTH(RETLN) RESP(RESP). GO SEND MESSAGE.
*      B    RETRVE7              BRANCH TO RETRVE7.
*
*ETRVE3 EQU *
      CLC  =C'      ',SYSID      IS SYSID BLANK.
      BE   RETRVE4              YES-BRANCH TO RETRVE4.
      EXEC CICS LINK PROGRAM('WMPAIM1') COMMAREA(WIZCOMM)          X
          LENGTH(RETLN) SYSID(SYSID) DATALENGTH(RETLN)          X
          RESP(RESP).      GO SEND MESSAGE.
      B    RETRVE7              BRANCH TO RETRVE7.

*
RETRVE4 EQU *
      EXEC CICS LINK PROGRAM('WMPAIM1') COMMAREA(WIZCOMM)          X
          LENGTH(RETLN)      DATALENGTH(RETLN)          X
          RESP(RESP).      GO SEND MESSAGE.

*
RETRVE7 EQU *
      CLC  RESP,DFHRESP(NORMAL) ANY ERROR.
      BE   RETRVE9              NO-BRANCH TO RETRVE9.
      BAL  RB,ERROR            PERFORM ERROR ROUTINE.
      B    RETURN              BRANCH TO RETURN.

*
RETRVE9 EQU *
      CLC  WIZERRM(35),=C'      ' WAS
      BE   RETURN              NO-BRANCH TO RETURN.
      MVC  WRTAREA(25),=C'DPWIZM-WIZMAIL SEND ERROR' MVE ERROR MESS
      ST   RB,SVRB            SVE CONTENTS OF REG 11.
      BAL  RB,WTOC            PERFORM WTOC ROUTINE.
      MVC  WRTAREA(L'WIZERRM),WIZERRM MVE WIZMAIL ERROR MESSAGE TO
      BAL  RB,WTOC            PERFORM WTOC ROUTINE.
      L    RB,SVRB            RESTORE CONTENTS OF REG 11.
      B    RETURN              BRANCH TO RETURN.

*
LINKED EQU *
      CLC  RETLEN,EIBCALEN      WAS EIBCALEN LENGTH 1500.
      BNE  RETURN              NO-BRANCH TO RETURN.
      EXEC CICS ADDRESS COMMAREA(R9).
*      CLC  =C'CICSPRD2',APPLID ARE WE RUNNING IN CICSPRD2.

```

```

*      BNE LINKED3          NO-BRANCH TO LINKED3.
*      EXEC CICS LINK PROGRAM('WMPAIM1') COMMAREA(WIZCOMM)          X
*      LENGTH(RETLN) RESP(RESP). GO SEND MESSAGE.
*      B LINKED7            BRANCH TO LINKED7.
*
*INKED3 EQU *
CLC    =C'      ',SYSID    IS SYSID BLANK.
BE     LINKED4            YES-BRANCH TO LINKED4.
EXEC   CICS LINK PROGRAM('WMPAIM1') COMMAREA(WIZCOMM)          X
      LENGTH(RETLN) SYSID(SYSID) DATALENGTH(RETLN)          X
      RESP(RESP).        GO SEND MESSAGE.
      B LINKED7            BRANCH TO LINKED7.
*
LINKED4 EQU *
EXEC   CICS LINK PROGRAM('WMPAIM1') COMMAREA(WIZCOMM)          X
      LENGTH(RETLN)          DATALENGTH(RETLN)          X
      RESP(RESP).        GO SEND MESSAGE.
*
LINKED7 EQU *
CLC    RESP,DFHRESP(NORMAL) ANY ERROR.
BE     LINKED9            NO-BRANCH TO LINKED9.
BAL    RB,ERROR          PERFORM ERROR ROUTINE.
B      RETURN            BRANCH TO RETURN.
*
LINKED9 EQU *
CLC    WIZERRM(35),=C'          ' WAS
BE     RETURN            NO-BRANCH TO RETURN.
ST     RB,SVRB          SVE CONTENTS OF REG 11.
MVC    WRTAREA(25),=C'DPWIZM-WIZMAIL SEND ERROR' MVE ERROR MESS
BAL    RB,WTOC          PERFORM WTOC ROUTINE.
MVC    WRTAREA(L'WIZERRM),WIZERRM MVE WIZMAIL ERROR MESSAGE TO
BAL    RB,WTOC          PERFORM WTOC ROUTINE.
L      RB,SVRB          RESTORE CONTENTS OF REG 11.
*
RETURN EQU *
EXEC   CICS RETURN.      RETURN TO CICS.
*
ERROR EQU *              ERROR ROUTINE.
MVC    WRTAREA(37),=C'DPWIZM-LINK ERROR TO WMPAIM1 OCCURRED'
*
ERROR3 EQU *              ERROR ROUTINE.
MVC    EIBFN1(8),EIBFN    MVE EIBFN/EIBRCODE TO EIBFN1.
MVC    EIBFN2(8),EIBRESP  MVE EIBRESP/EIBRESP2 TO EIBFN2.
LA     RD,SAVEAREA      LOAD ADDRESS OF SAVEAREA TO REG 13.
CALL   DPEIBC,(EIBFN1,EIBOUT1,EIBFN2,EIBOUT2)
ST     RB,SVRB          SVE CONTENTS OF REG 11.
BAL    RB,WTOC          PERFORM WTOC ROUTINE.
MVC    WRTAREA(15),=C'EIBFN/EIBRCODE='
MVC    WRTAREA+15(L'EIBOUT1),EIBOUT1

```

```

        BAL   RB,WTOC           PERFORM WTOC ROUTINE.
        MVC   WRTAREA(17),=C'EIBRESP/EIBRESP2='
        MVC   WRTAREA+17(L'EIBOUT2),EIBOUT2
        BAL   RB,WTOC           PERFORM WTOC ROUTINE.
        L     RB,SVRB           RESTORE CONTENTS OF REG 11.
        BR    RB                RETURN TO CALLER.
*
WTOC    EQU   *                WRITE TO CONSOLE ROUTINE.
        EXEC  CICS WRITE OPERATOR TEXT(WRTAREA)                X
          TEXTLENGTH(L'WRTAREA). WRITE MESSAGE TO SYSTEM CONSOLE.
        MVC   WRTAREA,WRTAREA-1 CLEAR WRTAREA.
        BR    RB                RETURN TO CALLER.
*
        DC   C' '              DON'T MOVE/REMOVE THIS STATEMENT.
WRTAREA DC   CL65' '          WRITE AREA.
*
SYSID   DC   CL4'&SYID'       SYSID SVE AREA WHERE WIZARD MAIL LIV
*
EIBFN1  DS   XL8              INPUT FIELD FOR CALL TO DPEIBC.
EIBOUT1 DS   CL17             OUTPUT FIELD FOR CALL TO DPEIBC.
EIBFN2  DS   XL8              INPUT FIELD FOR CALL TO DPEIBC.
EIBOUT2 DS   CL17             OUTPUT FIELD FOR CALL TO DPEIBC.
*
        DS   ØD
SVRB    DS   F                SVE AREA FOR REG 11.
SAVEAREA DS  18F              SVE AREA FOR CALL TO DPEIBC.
*
        LTORG
*
        END   DPWIZM

```

## DPEIBC

The DPEIBC subroutine converts the EIBFN and EIBRCODE in the EXEC interface block from hexadecimal to EBCDIC for CICS programs.

Two parameters must be passed, consisting of one field each, while a third and fourth parameter, each consisting of two fields, are optional. The first parameter must always be EIBFN.

The second parameter must be seventeen bytes, and is where the conversion of the EIBFN and EIBRCODE will be placed. The layout of the output will be as follows:

Field	Position	Value	Length
EIBFN	Ø1-Ø4		Ø4
	Ø5-Ø5	-	Ø1
EIBRCODE	Ø6-17		12

The optional third and fourth parameters consist of two fields each, as follows:

- The third parameter must contain two 4-byte hex fields consisting of the response (ie EIBRESP) field and the response two (ie EIBRESP2) field.
- The fourth parameter must contain two 8-byte fields plus an additional byte, for a total length of seventeen bytes, and is where the result of the conversion of the EIBRESP and EIBRESP2 fields will be placed. A hyphen is placed between each field.

Note that:

- The contents of the fields you move into the first parameter don't matter, as long as they're eight hex bytes long. This means that you could move two 4-byte hex fields. In other words, you can use this subroutine to convert any two 4-byte hex fields. But remember that the hyphen will then be placed incorrectly.
- The contents of the fields you move into the third parameter don't matter either, as long as they're also eight hex bytes long.
- The correct number of parameters in this subroutine is either two or four. If an incorrect number of parameters are passed, the first four bytes of the first parameter are returned with X'FFFFFFFF'.

### Calling sequences

The calling sequences follow.

For COBOL:

```
- CALL 'DPEIBC' USING EIBFN, OUTPUT.
```

or

```
- CALL 'DPEIBC' USING EIBFN, OUTPUT, PARAM3, PARAM4.
```

For ALC:

```
- LA 13,SAVEAREA (13 CAN ALSO BE R13 OR RD).  
CALL DPEIBC,(EIBFN,OUTPUT)
```

or

```
CALL DPEIBC,(EIBFN,OUTPUT,PARAM3,PARAM4)
```

.  
(MAINLINE PART OF PROGRAM).

SAVEAREA DC 18F'Ø'

### For RPGII:

```
- CALL 'DPEIBC'  
      PARM          EIBFN  
      PARM          OUTPUT
```

or

```
      PARM          PARAM3  
      PARM          PARAM4
```

An eighteen-word save area must be passed through register 13 by the user (STD COBOL LINKAGE).

### DPEIBC

DPEI TITLE 'DPEIBC - 1.Ø - CONVERTS EIBFN AND EIBRCODE CODES FROM HX  
EX TO EBCDIC.'

\*

```
DPEIBC CSECT Ø  
DPEIBC AMODE 31  
DPEIBC RMODE ANY  
ENTRY DPEIBC  
BALR 15,Ø LOAD TEMPORARY BASE.  
USING *,15 INFORM ASSEMBLER.  
SAVE (14,12)  
DROP 15 DROP TEMPORARY BASE.  
BALR 8,Ø LOAD BASE REG.  
USING *,8 INFORM ASSEMBLER.  
ST 13,SAVEAREA+4 STORE CALLERS RETURN ADDRESS.  
LA 13,SAVEAREA LOAD CALLERS REGISTERS.  
B EIBBEG BRANCH TO EIBBEG.
```

\*

DC C'DPEIBC STARTS HERE. ' INSERT EYE CATCHER.

\*

```
EIBBEG EQU *  
LM 3,4,Ø(1) LOAD ADDRESS OF EIB CODES AND OUTPUT  
STM 3,4,SVR3R4 SVE REGS 3 AND 4.  
MVI NUMPRM,X'ØØ' SET NUMBER OF PARAMETERS TO ZERO.  
SR 6,6 SET PARAMETER COUNT TO ZERO.
```

\*

```
EIBARG EQU *  
TM Ø(1),X'8Ø' ARE WE DONE.  
BO EIBLST YES-BRANCH TO EIBLST.
```

	LA	6,4(6)	INCREMENT REG 6 BY ONE (1).
	LA	1,4(1)	INCREMENT REG 1 TO NEXT PARAMETER.
	B	EIBARG	BRANCH TO EIBARG.
*			
EIBLST	EQU	*	
	SR	1,6	RESTORE REG 1.
	SRL	6,2	DIVIDE REG 6 BY 2.
	LA	6,1(6)	BUMP BY ONE FOR FIRST TIME.
	STC	6,NUMPRM	SAVE NUMBER OF PARAMETERS PASSED.
	CLI	NUMPRM,X'02'	WAS ONE (1) PARAMETER PASSED.
	BL	EIBERR	YES-BRANCH TO EIBERR. (ERROR).
	CLI	NUMPRM,X'04'	WAS MORE THAN FOUR (4) PARAMETERS PA
	BH	EIBERR	YES-BRANCH TO EIBERR. (ERROR).
	CLI	NUMPRM,X'02'	WERE TWO (2) PARAMETERS PASSED.
	BE	EIBNXT	YES-BRANCH TO EIBNXT.
	LM	5,6,8(1)	LOAD ADDRESSES OF THIRD AND FOURTH P
	STM	5,6,SVR5R6	SVE REG 5 AND 6.
	LA	9,8	LOAD COUNT OF BYTES TO CHANGE.
	SLR	1,1	CLEAR REG 1.
	SLR	2,2	CLEAR REG 2.
*			
EIBLOP1	EQU	*	
	IC	1,0(0,5)	LOAD BYTE FROM RESP FIELD.
	LR	2,1	PUT IT IN REG 2 ALSO.
	SRL	1,4	MVE 1ST 4 BITS TO LAST 4 BITS.
	IC	1,TRAN(1)	GET CHARACTER FOR HEX DIGIT.
	STC	1,0(0,6)	STORE IN OUTPUT ERROR CODES.
	LA	6,1(6)	INCREMENT OUTPUT ADDRESS BY ONE (1).
	N	2,=XL4'0F'	GET RIGHT NIBBLE ALONE.
	IC	2,TRAN(2)	GET CHARACTER FOR HEX DIGIT.
	STC	2,0(0,6)	STORE IN OUTPUT ERROR CODES.
	LA	6,1(6)	INCREMENT OUTPUT ADDRESS BY ONE (1).
	LA	5,1(5)	INCREMENT EIB CODES ADDRESS BY ONE (
	C	9,=F'5'	ARE WE AT THE END OF RESP FIELD.
	BNE	EIBEXT	NO-BRANCH TO EIBEXT.
	MVI	0(6),C'-'	MVE DASH (-).
	LA	6,1(6)	INCREMENT OUTPUT ADDRESS BY ONE (1).
*			
EIBEXT	EQU	*	
	BCT	9,EIBLOP1	BRANCH TO EIBLOP1 UNTIL REG 9 ZERO.
*			
EIBNXT	EQU	*	
	LA	9,8	LOAD COUNT OF BYTES TO CHANGE.
	SLR	1,1	CLEAR REG 1.
	SLR	2,2	CLEAR REG 2.
*			
EIBLOP3	EQU	*	
	IC	1,0(0,3)	LOAD BYTE FROM EIB CODES.
	LR	2,1	PUT IT IN REG 2 ALSO.
	SRL	1,4	MVE 1ST 4 BITS TO LAST 4 BITS.

```

        IC    1,TRAN(1)      GET CHARACTER FOR HEX DIGIT.
        STC   1,Ø(Ø,4)      STORE IN OUTPUT ERROR CODES.
        LA    4,1(4)        INCREMENT OUTPUT ADDRESS BY ONE (1).
        N     2,=XL4'ØF'    GET RIGHT NIBBLE ALONE.
        IC    2,TRAN(2)      GET CHARACTER FOR HEX DIGIT.
        STC   2,Ø(Ø,4)      STORE IN OUTPUT ERROR CODES.
        LA    4,1(4)        INCREMENT OUTPUT ADDRESS BY ONE (1).
        LA    3,1(3)        INCREMENT EIB CODES ADDRESS BY ONE (
        C     9,=F'7'       ARE WE AT THE END OF EIBFN.
        BNE   EIBEXT3       NO-BRANCH TO EIBEXT3.
        MVI   Ø(4),C'- '    MVE DASH (-).
        LA    4,1(4)        INCREMENT OUTPUT ADDRESS BY ONE (1).
*
EIBEXT3 EQU *
        BCT   9,EIBLOP3     BRANCH TO EIBLOP3 UNTIL REG 9 ZERO.
*
EIBRTN  EQU *
        SR    15,15         CLEAR REG 15.
        L     13,SAVEAREA+4 LOAD RETURN ADDRESS TO REG 13.
        RETURN (14,12),RC=(15) RETURN TO CALLER.
*
EIBERR  EQU *
        MVC   Ø(4,3),=X'FFFFFFFF' INDICATE PARAMETER ERROR.
        B     EIBRTN        BRANCH TO EIBRTN.
*
        DC    C'DPEIBC STORAGE HERE. ' INSERT EYE CATCHER.
*
NUMPRM  DS    X
TRAN     DC    C'Ø123456789ABCDEF'
SVR3R4  DS    2F
SVR5R6  DS    2F
SAVEAREA DC    18F'Ø'
*
        END

```

*Robert Botsis*  
*Senior Systems Programmer (USA)*

© Xephon 1999

Why not share your expertise and earn money at the same time? *CICS Update* is looking for JCL, macros, program code, etc, that experienced CICS users have written to make their life, or the lives of their users, easier. We will publish it (after vetting by our expert panel) and send you a cheque when the article is published. Articles can be of any length and can be sent or e-mailed to Robert Burgess at any of the addresses shown on page 2. Why not call now for a free copy of our *Notes for contributors*?

# CICS news

---

Iona Technologies has announced Orbix for CICS, enabling integration of CICS-based mainframe applications with the rest of the enterprise using standards-based CORBA technology.

Orbix for CICS runs inside the CICS transaction monitor and provides full application integration facilities with enterprise server systems on the mainframe, Unix, Windows, and Java platforms. It enables CICS applications to act as both CORBA servers and clients, enabling CICS to participate as a true Enterprise Application Server peer. Features include full ORB support within the CICS environment; COBOL, PL/I, and C++ language bindings; and native support for CICS Transaction Services 1.3.

For further information contact:  
Iona Technologies, 60 Aberdeen Avenue,  
Cambridge, MA 02138, USA.  
Tel: (617) 949 9000.  
URL: <http://www.iona.com>.

\* \* \*

Sterling Software has announced a new CICS/VSE Interface extension to its VM:Webgateway Web-to-host software, providing Web access to VSE data and applications through a GUI. VSE developers can carry out Web enhancements using CICS/VSE COBOL and other CICS command-level programming languages.

With the new interface, application developers can write CGI scripts using either CICS/VSE COBOL or REXX. The product includes a VSE tutorial demonstrating how

to create CGI scripts and how to Web-enable VSE applications. CGI scripts from the sample application can be copied and applied to real VSE applications to bring them to the Web.

For further information contact:  
Sterling Software, 1800 Alexander Bell  
Drive, Reston, VA 22091, USA.  
Tel: (703) 264 8000.  
Sterling Software, 1 Longwalk Road,  
Stockley Park, Uxbridge, Middlesex, UB11  
1DB.  
Tel: (0181) 867 8000.  
URL: <http://www.sterling.com>.

\* \* \*

CICS users can benefit from Tivoli's e-business management software for OS/390, allowing use of System/390 as the management server with service level improvement and business process view capabilities.

New products include Tivoli Manager for OS/390, Tivoli Service Desk for OS/390 Version 1.2, enhancements to Tivoli NetView for OS/390 and Tivoli Global Enterprise Manager, and an OS/390 version of Tivoli Enterprise. New direct support for OS/390 applications includes CICS, VTAM, and MQ, and an application toolkit for custom-built applications.

For further information contact:  
Tivoli Systems, 9442 Capitol of Texas  
Highway North, Arboretum Plaza One,  
Austin, TX 78759, USA.  
Tel: (512) 436 8000.  
URL: <http://www.tivoli.com>.



**xephon**